


HOW TO BUY STELO on Google Cloud Marketplace

## HOW TO BUY STELO ON GOOGLE CLOUD MARKETPLACE


#### Hello Stelo!

Need help getting started? This Google Cloud Marketplace Guide will walk you through the purchasing and deploying Stelo's Virtual Machine offer within the Google Cloud Commercial Marketplace.

- 1. Navigate to the <a>Stelo listing</a> on the Google Cloud Marketplace.
- 2. From the GCP Marketplace listing, click **Get Started** to open the Stelo Data Replicator Deployment landing page.




 Ensure you use a **Deployment Service Account** with the required roles as listed on the deployment page. Please note: The customer must deploy via an active Service Account.




## HOW TO BUY STELO ON GOOGLE CLOUD MARKETPLACE

- If you have an Existing Service Account, your Service Account will directly port onto the Deployment landing page.
- If you need to create a new Service Account, please follow the below steps:
- In the Google Cloud console, go to the **Create service account** page.
  - Select a Google Cloud project.
  - Enter a service account name to display in the Google Cloud console.
  - The Google Cloud console generates a service account ID based on this name. Edit the ID if necessary. You cannot change the ID later.
  - Optional: Enter a description of the service account.
- To set access controls, click Create and continue and continue to the next step.
  - o Choose the below roles to grant to the service account on the project:
    - roles/config.agent
    - roles/compute.admin
    - roles/iam.serviceAccountUser
- When you are done adding roles, click **Continue**.
- Click **Done** to finish creating the service account.
- 4. We recommend using n2d-highmem machine types or better for production deployments.
- 5. Click **Deploy**. Once the VM is created, it will appear as shown below:



# HOW TO BUY STELO ON GOOGLE CLOUD MARKETPLACE

6. Go to the **Details** tab to find links to Stelo services. Select the **Admin URL** to navigate to the Stelo Data Replicator landing page.



#### **Accessing Stelo Services:**

After the VM is deployed, access the Stelo services using the public IP address assigned to your VM:

- Replicator Service: http://[Public IP Address]:9119
- Control Center: http://[Public IP Address]:8080/SQDRManager